

# The PolyVision driver Release Notes

Rev. A,  
July, 2009

## Overview

---

This document contains release notes for the PolyVision driver 1.8.1

The PolyVision driver is part of an interactive system that connects to your computer and allows you to control, mark up, and save information on your computer from any PolyVision interactive device.

## What's New in 1.8.1?

---

### New Features

Version 1.8.1 adds these new features over version 1.7.2:

Feature	Description
eno mini	The new eno mini slate is fully supported.
Improved Line Rendering	The line rendering has been improved to provide smoother line strokes.
Multiple Pen Support	Up to 3 pens may be used concurrently in pen mode when using the Microsoft BT Stack. In cursor mode, the pens will compete for the system cursor. In pen mode, each writes independently
Driver API	There is now an API which third party applications can use to control the PolyVision driver.
Ink Mode	The driver now uses the PC and Mac pen ink input when available.
Additional Language Support	The PolyVision driver now supports Portuguese, Italian and Flemish.

## Downloads and Documentation

The latest drivers, Documentation, and release notes for the PolyVision driver is available online at:

<http://downloads.polyvision.com>

## Windows Minimum System Requirements

You should not attempt to install this software on Windows 3.1, Windows NT, Windows 95, Windows 98 or Windows ME. The minimum system requirements are:

- 500 MHz Pentium III (or equivalent) or faster
- 384MB RAM or more (1GB recommended for faster performance)
- Windows Vista, XP Sp2
- 800 by 600 display resolution or higher

## Macintosh Minimum System Requirements

You should not attempt to install this software on OS versions 10.1, 10.0, 9.2 and 8.6. The minimum system requirements are:

- 256 megabytes RAM recommended.
- A Power PC or G3 processor is the suggested minimum for electronic white boarding and projection. All Intel processors are supported.
- Thousands or millions of colors for proper color rendering.
- Operating System X versions 10.3.9 and above.

USB cables must not exceed 15 feet in length. More than one USB cable can be daisy-chained to create a longer cable, but the combined length should not exceed 15 feet without an active extender.

## Installing the Software

### Windows Vista, XP or Windows XP Tablet

You must have administrator-level access to install software.

Windows Vista or XP does not automatically start the installation when the PolyKey is installed so you will need to begin the process as follows:

1. Plug in the PolyKey
2. Browse to your E: drive (your drive letter may vary).
3. Click My Computer on your desktop and double-click the icon for the removable drive named 'PolyKey'.
4. Double-click the setup.exe and follow the instructions to install the PolyVision driver on your computer
5. When installation is complete, disconnect the PolyKey and if needed, connect your USB cable to your computer and PolyVision Product.

### For Installation on Macintosh Operating Systems

You must have administrator-level access in order to install software.

1. If your PolyVision product connects by cable, connect it now.
2. Plug in the PolyKey.
3. Double-click the drive.
4. Double-click the Macintosh folder.
5. Double-click on the PolyVision driver Icon.
6. Follow the onscreen instructions to install the PolyVision Driver.
7. When installation is complete, disconnect the PolyKey and if needed, connect your USB cable to your computer and PolyVision Product.
8. Restart the system. The PolyVision driver icon will appear in your menu bar.

## Support

---

If you require additional assistance contact PolyVision. PolyVision support is available at 1.800.620.POLY (7659), 678.542.3100 or support@polyvision.com.